


Junior Technician Job Notes


Task 01: Disabling Command Prompt access for Marketing OU:


Windows Server 2019:

- Server Manager – Tools – Group Policy Management.
- Find Marketing OU, right click then 'Create a GPO in this domain, and link it here ...'
- Enter a name of your choice.
- **Take a screenshot,**




- then edit the New GPO
- User Configuration – Policies – Administrative Templates – System – Prevent Access to the command prompt.
- Enable the above and **take a screenshot.**





-
- **Windows 10 Desktop:**
- Login as a member of the Marketing Group.
- Attempt to access the command prompt.
- **Take a screenshot of the error message.**





Task 02: Setup Roaming Profile for Lee Blake:

Step 01: Create a 'Roaming' Group.

Windows Server 2019:

- Server Manager – Tools – Active Directory Users and Computers.
- ACME.LOCAL – Area Managers.
- Create new group in area managers named ‘roaming’ (or similar).
- Add Lee Blake to the ‘roaming group’, **take a screenshot**.




Step 02: Create a share to store the roaming profiles and assign permissions.


Windows Server 2019:

- Server Manager – File and Storage Services
- Tasks – New Share
- SMB Share – Quick
- “Type a Custom Path” – Browse
- New Folder
- Use a name of your choice such as ‘Roaming’.
- Add \$ to the end of the share name to hide the share.
- “Enable access-based enumeration”.


- Customize Permissions, then 'Disable Inheritance and Convert inherited permissions to explicit permissions on these objects'.
- Remove All Permission entries except those in the screenshot shown here:




- Click Add
- Select Principle, then type roaming (or the name of the roaming group you created)



- Click OK
- Click 'Show Advanced Permissions'.
- Set the permissions as shown below, **take a screenshot**.






- Complete the New Share Wizard.

Step 03: Specify the roaming profile location for Lee Blake.

Windows Server 2019:


- Server Manager – Tools – Active Directory Users and Computers.
- ACME.LOCAL – Area Managers.
- Lee Blake – Properties – Profile.
- Enter profile path \\server\roaming\$\%username% (where roaming\$ is the name of your share), **take a screenshot**.





Step 04: Test the roaming profile.

Windows 10 Desktop/Windows 11:



- Login as Lee Blake on Windows 10 and create some files/folders on the desktop, in downloads and in documents. **Take some screenshots**.









-
- Logout of Windows 10.
- Login as Lee Blake on Windows 11 and check that the files folders are available. **Take some screenshots.**







Windows Server 2019:

- Take a screenshot of LBlakes profile folder within the Roaming\$ share.

